


Configuring Dial-up software (FreePPP):


1. Select FreePPP Setup from the FreePPP folder, the pull down menu or Control Panels. Click on the right-facing arrow in the lower-left corner of the window to display the configuration panels (see cursor in the diagram below).




2. On the General tab select **Allow application to open connection**, **Check line state when connected**, **Show alerts during connect and disconnect**.



3. Now click on the **Accounts** tab. Click **New**.



4. Enter FKBNet for **Account name**. Select **Directly** for **Connect**. Enter your **User name** and **Password**.




5. In the **Dialup** tab, enter 441 for the **Area code** and 295-0099 for the **Phone number**. Click **OK**

The screenshot shows the 'Options' tab of the 'Account' dialog box. The 'Dialup' tab is selected. The 'Main Number' section has 'Area code' set to 441 and 'Phone number' set to 295-0099. There are checkboxes for 'Dial area code' and 'Dial as long distance', both of which are unchecked. Below this are sections for 'Alternate Number 1' and 'Alternate Number 2', each with empty text boxes for 'Area code' and 'Phone number', and unchecked checkboxes for 'Dial area code' and 'Dial as long distance'. At the bottom right are 'Cancel' and 'OK' buttons.


6. Select the **Options** tab. Enter 205.136.31.3 for the **Primary DNS** and 205.136.31.20 as the **Secondary DNS** address. Click **OK**. Save the changes.

The screenshot shows the 'Options' tab of the 'Account' dialog box. The 'Options' tab is selected. The 'Domain name' field is empty. The 'Primary DNS' field contains 205.136.31.3 and the 'Secondary DNS' field contains 205.136.31.20. The checkbox 'Configure OT TCP/IP for this Account' is checked. Under 'IP address', the radio button 'Assigned by PPP server' is selected, and the '0.0.0.0' radio button is unselected. At the bottom right are 'Cancel' and 'OK' buttons.

7. Click the **Locations** tab. Click **Edit**.



8. If you have call waiting on the line, you should disable it by entering ***70**, in the **Dial prefix** box. If you need to dial a number to get an outside line you can enter it here as well. Otherwise, leave this box empty. Click **OK**.



Click on the square in the upper left-hand corner  to dismiss the FreePPP setup window.